

OFFICIAL CUSTOMER GUIDE

TRADE WITH AI V6.2.39

Dashboard & Button Guide

ਡੈਸ਼ਬੋਰਡ ਅਤੇ ਬਟਨ ਗਾਈਡ

Numbered ON/OFF behavior, safe button combinations, Hybrid order priority, OB Limit status meanings and quick-start recipes.


ਹਰ button ਦਾ ਨੰਬਰ-ਵਾਲੀਜ਼ ON/OFF behavior, safe combinations, Hybrid order priority, OB Limit status ਅਤੇ quick-start setup ਇਸ guide ਵੱਚ ਦੱਸਿ ਗਏ ਹਨ।

VERSION SCOPE

V6.2.39 Hybrid Arbiter

No Renko route - no dedicated 15M Structure button


Selected minute chart = execution timeframe



Prepared from the supplied V6.2.39 dashboard screenshot and the matching strategy behavior. Edition: 03
September 2026.

1. Read the current screenshot correctly

ਮੌਜੂਦਾ screenshot ਨੂੰ ਸਹੀ ਤਰੀਕੇ ਨਾਲ ਪੜ੍ਹੋ




Visible state	What it means / ਕੀ ਮਤਲਬ
STRATEGY OFF	No new automated entry can execute. The bottom status confirms SYSTEM INACTIVE. ਕੋਈ ਨਵੀਂ automated entry execute ਨਹੀਂ ਹੋ ਸਕਦੀ; ਹੇਠਾਂ SYSTEM INACTIVE ਵੀ ਇਹੀ ਦੱਸਦਾ ਹੈ।
BYPASS + AUTO SIGNAL ON	Bypass/SPEED 2 is the selected signal route. Bypass automatically keeps Auto Signal ON. Bypass/SPEED 2 selected ਹੈ ਅਤੇ Bypass Auto Signal ਨੂੰ ON ਰੱਖਦਾ ਹੈ।
HYBRID OFF	The central arbiter is not active. Signal/Bypass and OB Retest are isolated. Central arbiter active ਨਹੀਂ; Signal/Bypass ਅਤੇ OB Retest isolated ਹਨ।
OB LIMIT - MODE BLOCK	Correct status for Bypass with Hybrid OFF. It is not a missing-zone fault. Hybrid OFF ਨਾਲ Bypass ਚੱਲਣ ਸਮੇਂ ਇਹ ਸਹੀ status ਹੈ; zone fault ਨਹੀਂ।
SMART TARGET ON	Future single-target trades use dynamic target/profit-secure management. It does not turn entries on. Future single-target trades ਲਈ dynamic target management active ਹੈ; ਇਹ entry master switch ਨਹੀਂ।
LIQUIDITY / NEWS / SESSION OFF	Those optional filters are not active. EXTREME LOCK remains the visible VWAP-distance protection. ਇਹ optional filters active ਨਹੀਂ; EXTREME LOCK VWAP-distance safety ਵਜੋਂ active ਹੈ।

Customer rule / ਗਾਹਕ ਲਈ ਨਿਯਮ: Green or colored mode buttons show selected preferences, but automated trading still requires STRATEGY ON, ITRADE ON, MTF ON, HOLD above zero and ALT ON.

2. Numbered dashboard map - buttons 1 to 16

ਉਪਰਲੇ buttons ਦੀ ਨੰਬਰ-ਵਾਈਜ਼ ਪਛਾਣ




1	STRATEGY Master execution
2	AI ANALYZER Enhanced quality filter
3	LONG Permit buys
4	CLOSE Manual close
5	SHORT Permit sells
6	BE Manual breakeven
7	MTF Context selector
8	ITRADE Automation permission
9	HOLD Simple persistence
10	M. TP T1/T2/T3 targets
11	TRAIL SL Automatic stop trail
12	TP TRAIL Profit follow mode
13	AUTO BE Automatic breakeven
14	AI PANEL Show/hide report
15	ALT Alternate after fills
16	NEWS High-impact lock

Execution-timeframe rule: MTF supplies context only. A 1-minute, 5-minute, 15-minute, 60-minute or 240-minute chart executes from that selected minute chart. Renko is intentionally outside this version.

Execution timeframe ਨਜ਼ਿਮ: MTF ਸਰਿਫ context ਦਿੰਦਾ ਹੈ। ਜਹਿਜ਼ਾ minute chart selected ਹੈ, execution ਉਸੇ ਤੋਂ ਹੁੰਦੀ ਹੈ। ਇਸ version ਵਿੱਚ Renko route ਨਹੀਂ ਹੈ।

3. Numbered dashboard map - buttons 17 to 27

Execution modes, Hybrid, OB Limit ਅਤੇ status panel



17	AUTO SIGNAL Confirmed signal + countdown
18	TREND CATCH Exclusive continuation route
19	SMART TARGET Dynamic exit manager
20	BYPASS Fast live signal route
21	TURBO Exclusive immediate trend route
22	HYBRID Central order arbiter
23	OB RETEST LIMIT Qualified Major Zone limit
24	LIQUIDITY MAP EQH/EQL soft priority
25	SESSION Trading time window
26	EXTREME LOCK VWAP distance protection
27	AI REALTIME REPORT Final truth/status panel

MODE BLOCK is an instruction, not an error. Outside Hybrid, OB Retest can submit only in Simple Mode. Inside Hybrid, Bypass/Auto Signal/Simple and OB Retest share one safe order owner.

MODE BLOCK error ਨਹੀਂ। Hybrid ਤੋਂ ਬਾਹਰ OB Retest ਸਹਿਫ਼ Simple Mode ਵੱਲੋਂ submit ਕਰਦਾ ਹੈ; Hybrid ਵੱਲੋਂ ਸਾਰੇ routes ਇੱਕ safe order owner share ਕਰਦੇ ਹਨ।

4. Button details - system foundation

System ਅਤੇ permission buttons

1

STRATEGY

EN: Master execution switch. ON accepts new trades; OFF makes the system inactive and resets execution modes while preserving LONG/SHORT permissions.

ਪੰਜਾਬੀ: ਇਹ master execution switch ਹੈ। ON ਹੋਣ ਤੇ ਨਵੀਆਂ trades ਲਈ system active ਹੁੰਦਾ ਹੈ। OFF ਕਰਨ ਨਾਲ execution modes reset ਹੁੰਦੇ ਹਨ, ਪਰ LONG/SHORT permissions ਬਚੀਆਂ ਰਹਿੰਦੀਆਂ ਹਨ।

2

AI ANALYZER

EN: Adds the enhanced analyzer/history-clear confirmation and shows analyzer state. It is a quality filter, not the master execution switch.

ਪੰਜਾਬੀ: ਇਹ enhanced analyzer ਅਤੇ history-clear confirmation ਜੋੜਦਾ ਹੈ। ਇਹ quality filter ਹੈ, master execution switch ਨਹੀਂ।

3

LONG

EN: ON permits BUY/LONG entries. OFF blocks all new long entries in every route.

ਪੰਜਾਬੀ: ON ਹੋਣ ਤੇ BUY/LONG entries allowed ਹਨ। OFF ਹੋਣ ਤੇ ਹਰ mode ਵਿੱਚ ਨਵੀਂ long entry block ਰਹੇਗੀ।

4

CLOSE

EN: Requests a manual close of the strategy position and consumes the active setup so the same signal cannot immediately re-enter.

ਪੰਜਾਬੀ: Strategy position ਨੂੰ manual close ਕਰਨ ਦੀ request ਭੇਜਦਾ ਹੈ ਅਤੇ active setup consume ਕਰਦਾ ਹੈ, ਤਾਂ ਜੋ ਉਹੀ signal ਤੁਰੰਤ re-entry ਨਾ ਕਰੇ।

5

SHORT

EN: ON permits SELL/SHORT entries. OFF blocks all new short entries in every route.

ਪੰਜਾਬੀ: ON ਹੋਣ ਤੇ SELL/SHORT entries allowed ਹਨ। OFF ਹੋਣ ਤੇ ਹਰ mode ਵਿੱਚ ਨਵੀਂ short entry block ਰਹੇਗੀ।

6

BE

EN: Manual breakeven request for an open position. The stop is moved only to a price that remains valid relative to the live market.

ਪੰਜਾਬੀ: Open position ਲਈ manual breakeven request ਹੈ। Stop ਸਹਿਫ਼ live market ਦੇ ਮੁਤਾਬਕ valid price ਉੱਤੇ ਹੀ move ਹੁੰਦਾ ਹੈ।

7

MTF

EN: Cycles OFF, 1M, 5M and 15M context sync. This does not change the execution chart: the selected minute chart remains the execution timeframe.

ਪੰਜਾਬੀ: OFF, 1M, 5M ਅਤੇ 15M context sync ਵਿੱਚ cycle ਕਰਦਾ ਹੈ। Execution timeframe ਨਹੀਂ ਬਦਲਦਾ; ਜਹਿੜਾ minute chart ਚੁਣਿਆ ਹੈ, entry ਉਸੇ chart ਤੋਂ ਹੁੰਦੀ ਹੈ।

8

iTRADE

EN: Automated-entry permission. ON is required before STRATEGY can arm; OFF blocks new automated entries.

ਪੰਜਾਬੀ: Automated entry permission ਹੈ। STRATEGY arm ਕਰਨ ਲਈ ON ਲਾਜ਼ਮੀ ਹੈ। OFF ਹੋਣ ਤੇ ਨਵੀਆਂ automatic entries block ਹਨ।

9

HOLD

EN: Cycles OFF, 5s, 10s and 15s for Simple setup persistence. A non-zero HOLD is required to arm STRATEGY. Auto Signal keeps its own fixed confirmation timing.

ਪੰਜਾਬੀ: Simple setup persistence ਲਈ OFF, 5s, 10s ਅਤੇ 15s cycle ਹੈ। STRATEGY arm ਕਰਨ ਲਈ non-zero HOLD ਲਾਜ਼ਮੀ ਹੈ। Auto Signal ਦੀ ਆਪਣੀ fixed confirmation timing ਰਹਿੰਦੀ ਹੈ।

5. Button details - management and signals

Trade management ਅਤੇ signal buttons

10

M. TP

EN: Uses independent T1/T2/T3 targets. It is isolated from Smart Target and OB Retest; enabling it turns TP Trail off.
ਪੰਜਾਬੀ: ਵੱਖਰੇ T1/T2/T3 targets ਵਰਤਦਾ ਹੈ। Smart Target ਅਤੇ OB Retest ਨਾਲ isolated ਹੈ; ਇਸਨੂੰ ON ਕਰਨ ਨਾਲ TP Trail OFF ਹੋ ਜਾਂਦਾ ਹੈ।

11

TRAIL SL

EN: Automatically tightens the protective stop behind the best price by the configured tick distance. It does not loosen the stop.
ਪੰਜਾਬੀ: Configured tick distance ਅਨੁਸਾਰ best price ਦੇ ਪੱਛੇ protective stop tighten ਕਰਦਾ ਹੈ। Stop ਨੂੰ ਢਲਿਆ ਨਹੀਂ ਕਰਦਾ।

12

TP TRAIL

EN: Single-target follow mode. It activates after the configured profit and follows behind best price; mouse wheel over the button adjusts the distance. Incompatible with Smart Target, Multi-TP and OB Retest.
ਪੰਜਾਬੀ: Single-target follow mode ਹੈ। Configured profit ਤੋਂ ਬਾਅਦ best price ਦੇ ਪੱਛੇ follow ਕਰਦਾ ਹੈ; button ਉੱਤੇ mouse wheel ਨਾਲ distance ਬਦਲਦੀ ਹੈ। Smart Target, Multi-TP ਅਤੇ OB Retest ਨਾਲ compatible ਨਹੀਂ।

13

AUTO BE

EN: Automatically moves the stop to breakeven plus the configured offset once the profit trigger is reached.
ਪੰਜਾਬੀ: Profit trigger ਮਲਿਣ ਤੋਂ ਬਾਅਦ stop ਨੂੰ ਆਪਣੇ ਆਪ breakeven plus configured offset ਉੱਤੇ ਲਿਆਉਂਦਾ ਹੈ।

14

AI PANEL

EN: Shows or hides the realtime report panel only. Hiding the panel does not disable the strategy.
ਪੰਜਾਬੀ: ਸਰਿਫ਼ realtime report panel show/hide ਕਰਦਾ ਹੈ। Panel hide ਕਰਨ ਨਾਲ strategy disable ਨਹੀਂ ਹੁੰਦੀ।

15

ALT

EN: Fill-based alternating sequence. After an actual LONG fill, only SHORT is allowed next; after an actual SHORT fill, only LONG is allowed. Canceled or unfilled orders do not consume the turn.
ਪੰਜਾਬੀ: Fill-based alternate sequence ਹੈ। Actual LONG fill ਤੋਂ ਬਾਅਦ ਅਗਲੀ side ਸਰਿਫ਼ SHORT; actual SHORT fill ਤੋਂ ਬਾਅਦ ਅਗਲੀ side ਸਰਿਫ਼ LONG। Canceled ਜਾਂ unfilled order turn consume ਨਹੀਂ ਕਰਦਾ।

16

NEWS

EN: When ON, loads the next USD high-impact event and applies the scheduled news lock/alert. OFF clears that news lock state.
ਪੰਜਾਬੀ: ON ਹੋਣ ਤੇ ਅਗਲਾ USD high-impact event load ਕਰਕੇ scheduled news lock/alert ਲਗਦਾ ਹੈ। OFF ਕਰਨ ਨਾਲ news lock state clear ਹੋ ਜਾਂਦੀ ਹੈ।

17

AUTO SIGNAL

EN: Uses a fresh confirmed chart signal with the fixed signal confirmation countdown. Outside Hybrid, it is an isolated execution route and OB Retest is mode-blocked.
ਪੰਜਾਬੀ: Fresh confirmed chart signal ਨੂੰ fixed confirmation countdown ਨਾਲ ਵਰਤਦਾ ਹੈ। Hybrid ਤੋਂ ਬਾਹਰ ਇਹ isolated route ਹੈ ਅਤੇ OB Retest mode-block ਰਹਿੰਦਾ ਹੈ।

18

TREND CATCH

EN: Exclusive confirmed impulse/continuation route. It turns Auto Signal, Bypass and Turbo off and cannot run with Hybrid.
ਪੰਜਾਬੀ: Exclusive confirmed impulse/continuation route ਹੈ। Auto Signal, Bypass ਅਤੇ Turbo OFF ਕਰਦਾ ਹੈ ਅਤੇ Hybrid ਨਾਲ ਨਹੀਂ ਚੱਲਦਾ।

6. Button details - Hybrid, OB and filters

Hybrid, OB Limit ਅਤੇ protection buttons

19

SMART TARGET

EN: For future single-target trades, dynamically extends the target and can secure profit. Change only while FLAT. Protective SL logic remains active.

ਪੰਜਾਬੀ: Future single-target trades ਲਈ target dynamically extend ਕਰਦਾ ਅਤੇ profit secure ਕਰ ਸਕਦਾ ਹੈ। ਸਰਿਫ FLAT ਹੋਣ ਤੇ ਬਦਲੇ। Protective SL logic active ਰਹਿੰਦੀ ਹੈ।

20

BYPASS

EN: Fastest published-signal route. It automatically turns Auto Signal ON, uses a fresh live signal first and a closed-candle fallback, and skips the 5-second signal countdown. Universal safety gates still apply.

ਪੰਜਾਬੀ: ਸਭ ਤੋਂ fast published-signal route ਹੈ। Auto Signal ਆਪਣੇ ਆਪ ON ਕਰਦਾ ਹੈ, ਪਹਿਲਾਂ fresh live signal ਅਤੇ ਫਰਿ closed-candle fallback ਵਰਤਦਾ ਹੈ, 5-second signal countdown ਨਹੀਂ ਲਗਦਾ। Universal safety gates ਫਰਿ ਵੀ ਲਾਗੂ ਹਨ।

21

TURBO

EN: Exclusive immediate trend-side route. It ignores soft OB confirmation but keeps opposing-OB and hard risk locks. It cannot run with Hybrid and turns other signal modes off.

ਪੰਜਾਬੀ: Exclusive immediate trend-side route ਹੈ। Soft OB confirmation ignore ਕਰਦਾ ਹੈ, ਪਰ opposing-OB ਅਤੇ hard risk locks ਰਹਿੰਦੇ ਹਨ। Hybrid ਨਾਲ ਨਹੀਂ ਚੱਲਦਾ ਅਤੇ ਹੋਰ signal modes OFF ਕਰਦਾ ਹੈ।

22

HYBRID

EN: Central order arbiter, not a new signal formula. Priority is Bypass, Auto Signal, Simple, then OB Retest. It allows one entry owner and requires broker cancel confirmation before a reserved market entry.

ਪੰਜਾਬੀ: ਇਹ central order arbiter ਹੈ, ਨਵਾਂ signal formula ਨਹੀਂ। Priority ਹੈ: Bypass, Auto Signal, Simple, ਫਰਿ OB Retest। ਇੱਕ ਹੀ entry owner ਰੱਖਦਾ ਹੈ ਅਤੇ reserved market entry ਤੋਂ ਪਹਿਲਾਂ broker cancel confirmation ਲਾਜ਼ਮੀ ਹੈ।

23

OB RETEST LIMIT

EN: Parks a qualified limit near a Major Zone only after proximity, reaction, analyzer, ALT, path, risk and R:R checks. It runs in Simple or Hybrid only. MODE BLOCK means the selected execution mode is incompatible, not that the button is broken.

ਪੰਜਾਬੀ: Major Zone ਨੇੜੇ limit ਸਰਿਫ proximity, reaction, analyzer, ALT, path, risk ਅਤੇ R:R checks ਤੋਂ ਬਾਅਦ park ਹੁੰਦਾ ਹੈ। ਇਹ ਸਰਿਫ Simple ਜਾਂ Hybrid ਵੱਲੋਂ ਚੱਲਦਾ ਹੈ। MODE BLOCK ਦਾ ਮਤਲਬ incompatible mode ਹੈ, button fault ਨਹੀਂ।

24

LIQUIDITY MAP

EN: Optional EQH/EQL liquidity map and soft priority bonus for new OB candidates. It never removes the base safety gates.

ਪੰਜਾਬੀ: Optional EQH/EQL liquidity map ਅਤੇ ਨਵੇਂ OB candidates ਲਈ soft priority bonus ਹੈ। Base safety gates ਕਦੇ remove ਨਹੀਂ ਕਰਦਾ।

25

SESSION

EN: Cycles OFF, ASIA, LONDON and NY. A selected session restricts both normal entries and OB Retest to that session window; OFF removes the session restriction.

ਪੰਜਾਬੀ: OFF, ASIA, LONDON ਅਤੇ NY ਵੱਲੋਂ cycle ਕਰਦਾ ਹੈ। Selected session normal entries ਅਤੇ OB Retest ਦੋਨਾਂ ਨੂੰ ਉਸ window ਤੱਕ restrict ਕਰਦੀ ਹੈ; OFF ਨਾਲ session restriction ਹਟਦੀ ਹੈ।

26

EXTREME LOCK

EN: VWAP-distance protection. When configured above zero and ON, entries too far from VWAP are blocked.

ਪੰਜਾਬੀ: VWAP-distance protection ਹੈ। Points zero ਤੋਂ ਉੱਪਰ configured ਹੋਣ ਅਤੇ button ON ਹੋਣ ਤੇ VWAP ਤੋਂ ਬਹੁਤ ਦੂਰ entries block ਹੁੰਦੀਆਂ ਹਨ।

27

AI REALTIME REPORT

EN: Status display, not an entry button. Read Asset, Mode, Execution TF, Position, analyzer/link state, OB Retest state, Liquidity Map, STRATEGY and the final Status line before expecting an order.

ਪੰਜਾਬੀ: ਇਹ status display ਹੈ, entry button ਨਹੀਂ। Order ਦੀ ਉਮੀਦ ਤੋਂ ਪਹਿਲਾਂ Asset, Mode, Execution TF, Position, analyzer/link state, OB Retest, Liquidity Map, STRATEGY ਅਤੇ final Status line ਪੜ੍ਹੋ।

7. Recommended button recipes

ਕਹਿੜੇ mode ਲਈ ਕਹਿੜੇ buttons ON/OFF ਕਰਨੇ ਹਨ

Safe common base / ਸਾਂਝਾ safe base: FLAT position, correct account/instrument/quantity/SL/TP, LONG/SHORT as desired, MTF ON, iTRADE ON, HOLD 5s or higher, ALT ON, EXTREME LOCK ON, and STRATEGY ON last.

Mode	Mode buttons	Expected behavior / ਨਤੀਜਾ
Simple + optional OB	Auto Signal OFF Bypass OFF Trend Catch OFF Turbo OFF Hybrid OFF OB Limit ON optional	Quality-first Simple entries; OB Limit may work independently. Simple entries ਅਤੇ optional Major-Zone limit।
Auto Signal	Auto Signal ON Bypass OFF Hybrid OFF	Confirmed signal with fixed countdown. OB displays MODE BLOCK. Confirmed signal countdown ਨਾਲ; OB blocked।
Bypass	Bypass ON Auto Signal ON automatically Hybrid OFF	Fast live signal with closed-candle fallback. OB displays MODE BLOCK. Fast live signal; OB isolated ਅਤੇ blocked।
Full Hybrid (recommended for combined routes)	Hybrid ON OB Limit ON Auto Signal ON Bypass optional ON	One arbiter coordinates Bypass, Auto Signal, Simple and OB Retest. ਇੱਕ arbiter ਚਾਰਾਂ routes ਨੂੰ safely coordinate ਕਰਦਾ ਹੈ।
Trend Catch	Hybrid OFF Trend Catch ON	Exclusive continuation route; Signal, Bypass and Turbo are turned OFF. Exclusive continuation route।
Turbo	Hybrid OFF Turbo ON	Exclusive immediate trend-side route; other signal modes are turned OFF. Exclusive immediate trend route।

Configure modes while STRATEGY is OFF and position is FLAT; turn STRATEGY ON last. This prevents an unintended immediate entry while you are still changing buttons.
Modes ਨੂੰ STRATEGY OFF ਅਤੇ position FLAT ਹੋਣ ਸਮੇਂ configure ਕਰੋ; STRATEGY ਸਭ ਤੋਂ ਅੰਤ ਵੱਲੋਂ ON ਕਰੋ।

8. Hybrid order priority and cancel-confirm handoff

Hybrid ਵੱਲੋਂ order ਪਹਿਲਾਂ ਕਹਿਤਾ ਜਾਣਗਾ



Step	Event	System action / System ਕੀ ਕਰਦਾ ਹੈ
1	OB Limit is working	Pending limit remains the current order owner. Pending limit ਹੁਣ current owner ਹੈ।
2	Fresh higher-priority signal arrives	Hybrid reserves that exact event once; it does not send a second entry. Hybrid exact event reserve ਕਰਦਾ ਹੈ, ਦੂਜੀ entry ਨਹੀਂ ਭੇਜਦਾ।
3	Cancel is requested	Market entry waits. Cancel request alone is not confirmation. Market entry wait ਕਰਦੀ ਹੈ; cancel request confirmation ਨਹੀਂ।
4A	Broker confirms Cancelled	Hybrid revalidates connection, account, FLAT position, direction permission, ALT, opposing OB, age and adverse chase. Only then may it submit. ਸਾਰੇ gates ਦੁਬਾਰਾ pass ਹੋਣ ਤੇ ਹੀ market order submit ਹੋ ਸਕਦਾ ਹੈ।
4B	Limit fills first	The limit wins. Reserved signal is discarded; no duplicate market entry is sent. Limit fill ਜਿਤਦਾ ਹੈ; reserved signal discard ਹੁੰਦਾ ਹੈ ਅਤੇ duplicate entry ਨਹੀਂ।
5	Signal becomes invalid or stale	No market entry. Old shadow zone is not blindly restored; the live OB engine must qualify it again. Market entry ਨਹੀਂ; ਪੁਰਾਣਾ zone blind restore ਨਹੀਂ ਹੁੰਦਾ, fresh qualification ਲਾਜ਼ਮੀ ਹੈ।

The cancel-confirm wait can cost a moment, but it prevents two live entry owners. The system never promises that every visible signal or Major Zone will become an order.

Cancel-confirm wait ਬੇੜ੍ਹਾ ਸਮਾਂ ਲੈ ਸਕਦੀ ਹੈ, ਪਰ ਦੋ live entry owners ਤੋਂ ਬਚਾਉਂਦੀ ਹੈ। ਹਰ visible signal ਜਾਂ Major Zone ਦਾ order ਬਣਨਾ guarantee ਨਹੀਂ।

9. Compatibility and status messages

ਕਹਿੰਗੇ features ਇਕੱਠੇ ਚੱਲ ਸਕਦੇ ਹਨ

Combination	Allowed?	Meaning / ਮਤਲਬ
Smart Target + Auto BE/Trail SL	YES	Smart Target manages profit; protective stop tools may still tighten risk. Profit ਅਤੇ protective stop ਦੇ ਵੱਖਰੇ roles ਹਨ।
Smart Target + Multi-TP	NO	Turn one off before enabling the other. ਇੱਕ ਨੂੰ OFF ਕਰਕੇ ਦੂਜਾ ON ਕਰੋ।
Smart Target + TP Trail	NO	Only one dynamic profit manager may own the trade. ਇੱਕ ਹੀ dynamic profit manager।
OB Retest + Multi-TP	NO	OB Retest uses one structure-derived target. OB Retest single structural target ਵਰਤਦਾ ਹੈ।
OB Retest + TP Trail	NO	Turn TP Trail off before OB Retest. OB Retest ਤੋਂ ਪਹਿਲਾਂ TP Trail OFF ਕਰੋ।
OB Retest + Auto Signal/Bypass	HYBRID ONLY	HYBRID ON is required for shared operation. Shared operation ਲਈ HYBRID ON ਲਾਜ਼ਮੀ।
Turbo/Trend Catch + Hybrid	NO	Turbo and Trend Catch remain exclusive. ਦੋਵੇਂ exclusive modes ਹਨ।
Liquidity Map + any mode	YES	Optional soft context; it does not bypass safety. Optional soft context; safety bypass ਨਹੀਂ।

Panel message	Interpretation / ਵਿਆਖਿਆ
SYSTEM INACTIVE	STRATEGY is OFF. STRATEGY OFF ਹੈ।
MODE BLOCK	OB Retest is enabled as a preference, but the current non-Hybrid execution mode cannot use it. OB Retest preference ON ਹੈ, ਪਰ current non-Hybrid mode ਇਸਨੂੰ ਵਰਤ ਨਹੀਂ ਸਕਦਾ।
SCANNING	Mode is allowed; the engine is waiting for all live zone and safety gates. Mode allowed ਹੈ; engine live zone ਅਤੇ safety gates ਦੀ ਉਡੀਕ ਕਰ ਰਹਿਾ ਹੈ।
CANCEL PENDING	A broker cancel callback is required before a Hybrid handoff can continue. Hybrid handoff ਤੋਂ ਪਹਿਲਾਂ broker ਦਾ cancel callback ਲਾਜ਼ਮੀ ਹੈ।
TIME CHART REQUIRED	This build supports minute-based execution charts, not Renko. ਇਹ build minute-based execution charts ਲਈ ਹੈ, Renko ਲਈ ਨਹੀਂ।
OUTSIDE ASIA/LONDON/NY	The selected session window is not currently active. Selected session window ਇਸ ਵੇਲੇ active ਨਹੀਂ।

10. Customer quick-start checklist

Live order ਤੋਂ ਪਹਿਲਾਂ ਇਹ checklist ਪੂਰੀ ਕਰੋ

#	Check	Action / ਕੀ ਕਰਨਾ ਹੈ
1	Use a supported minute chart	Choose 1M, 5M, 15M, 60M or 240M. The screenshot uses 5M. 1M, 5M, 15M, 60M ਜਾਂ 240M ਚੁਣੋ; screenshot 5M ਹੈ।
2	Verify trading details	Correct account, instrument, order quantity, stop loss and target settings. Account, instrument, quantity, stop loss ਅਤੇ target verify ਕਰੋ।
3	Set permissions	LONG and/or SHORT ON; iTRADE ON; MTF ON; HOLD 5s/10s/15s; ALT ON. ਚਾਹੀਦੀ direction ਨਾਲ ਇਹ ਸਾਰੇ base permissions ON ਕਰੋ।
4	Choose one execution architecture	Simple, Auto Signal, Bypass, Full Hybrid, Trend Catch or Turbo. ਇਨ੍ਹਾਂ ਵਿੱਚੋਂ ਇੱਕ execution architecture ਚੁਣੋ।
5	Choose one profit architecture	Fixed target, Smart Target, Multi-TP or TP Trail. Do not mix blocked managers. ਇੱਕ profit architecture ਚੁਣੋ; blocked managers mix ਨਾ ਕਰੋ।
6	Add optional filters	NEWS, LIQUIDITY MAP and SESSION as required; keep EXTREME LOCK configured and ON for distance safety. ਲੋੜ ਮੁਤਾਬਕ optional filters ਅਤੇ distance safety ਲਈ EXTREME LOCK ਵਰਤੋ।
7	Read the panel	Confirm Mode, Execution TF, Indicator Link SYNC, Smart Analyzer state, OB Retest state and final Status. Order ਤੋਂ ਪਹਿਲਾਂ panel ਦੀਆਂ ਇਹ fields verify ਕਰੋ।
8	Turn STRATEGY ON last	The startup grace consumes old bridge events and waits for fresh signals. Startup grace ਪੁਰਾਣੇ events consume ਕਰਕੇ fresh signal ਦੀ wait ਕਰਦੀ ਹੈ।
9	Watch NinjaTrader order state	During Hybrid handoff, wait for Cancelled confirmation; if the limit fills first, the limit owns the trade. Hybrid handoff ਵਿੱਚ Cancelled confirmation ਦੇਖੋ; ਪਹਿਲਾਂ limit fill ਹੋਵੇ ਤਾਂ ਉਹੀ trade owner ਹੈ।
10	Test before scaling	Use Market Replay or Sim101 first, then the smallest live size. Save logs/screenshots for any unexpected block. ਪਹਿਲਾਂ Replay/Sim101, ਫਿਰ smallest live size; unexpected block ਦੀ log/screenshot ਸੰਭਾਲੋ।

Suggested full Hybrid sequence from this screenshot: keep STRATEGY OFF and position FLAT -> HYBRID ON -> verify OB RETEST - HYBRID ON -> keep AUTO SIGNAL ON -> keep BYPASS ON only if fast live execution is desired -> confirm ALT/MTF/iTRADE/HOLD -> STRATEGY ON last.

ਇਸ screenshot ਤੋਂ Full Hybrid sequence: STRATEGY OFF ਅਤੇ FLAT -> HYBRID ON -> OB RETEST - HYBRID ON verify ਕਰੋ -> AUTO SIGNAL ON -> fast live execution ਚਾਹੀਦੀ ਹੋਵੇ ਤਾਂ BYPASS ON -> ALT/MTF/iTRADE/HOLD verify -> STRATEGY ਸਭ ਤੋਂ ਅੰਤ ON।

11. Safety notes and customer expectations

ਜ਼ਰੂਰੀ safety notes

Rule	Customer guidance / ਗਾਹਕ ਲਈ ਹਦਾਇਤ
No guaranteed entry	A visible BUY/SELL label, 85%-100% Major Zone or chart touch is not sufficient by itself. Direction, proximity, reaction, path, target, R:R, ALT, session, news and risk gates may still block. Visible signal ਜਾਂ 85%-100% zone ਆਪਣੇ ਆਪ order ਦੀ guarantee ਨਹੀਂ; ਹੋਰ gates ਵੀ pass ਹੋਣੇ ਲਾਜ਼ਮੀ ਹਨ।
No guaranteed profit	The system cannot guarantee minimum stop loss or maximum profit. Volatility, slippage, gaps, rejected orders and connectivity can change results. Minimum SL ਜਾਂ maximum profit ਦੀ guarantee ਨਹੀਂ; volatility, slippage, gaps, rejection ਅਤੇ connection result ਬਦਲ ਸਕਦੇ ਹਨ।
One owner	Hybrid deliberately waits for confirmed cancellation before replacing a working limit with a higher-priority market entry. Hybrid working limit ਨੂੰ replace ਕਰਨ ਤੋਂ ਪਹਿਲਾਂ confirmed cancellation ਦੀ wait ਕਰਦਾ ਹੈ।
Change modes while FLAT	Hybrid, Smart Target and OB Retest include FLAT-state protections. Avoid changing order architecture while a trade or handoff is active. Mode ਜਾਂ order architecture ਸਰਿਫ਼ FLAT ਅਤੇ handoff inactive ਹੋਣ ਸਮੇਂ ਬਦਲੋ।
Manual supervision	Monitor account, connection, order state and protective orders. Use CLOSE for a position; separately verify any working order in NinjaTrader's Orders/Chart Trader view. Account, connection, orders ਅਤੇ protective orders monitor ਕਰੋ; working order ਨੂੰ Orders/Chart Trader ਵੱਲੋਂ ਵੱਖਰੇ ਤੌਰ ਤੇ verify ਕਰੋ।
Version boundary	This guide applies to V6.2.39. Renko and the removed dedicated 15M Structure route are not part of this build. ਇਹ guide ਸਰਿਫ਼ V6.2.39 ਲਈ ਹੈ; Renko ਅਤੇ dedicated 15M Structure route ਇਸ build ਵੱਲੋਂ ਨਹੀਂ।

Before real-money use, validate the exact instrument, session template, commission, latency and fill behavior in Market Replay/Sim101. Past or replay performance does not guarantee future results.
Real-money ਤੋਂ ਪਹਿਲਾਂ instrument, session template, commission, latency ਅਤੇ fills ਨੂੰ Market Replay/Sim101 ਵੱਲੋਂ validate ਕਰੋ। Past ਜਾਂ replay performance future result ਦੀ guarantee ਨਹੀਂ।

END OF GUIDE

Trade with AI V6.2.39 - Dashboard & Button Guide - English + ਪੰਜਾਬੀ